

NAME

`dvips` – convert a TeX DVI file to PostScript

SYNOPSIS

`dvips` [*OPTIONS*] *file* [*.dvi*]

DESCRIPTION

THIS MAN PAGE IS OBSOLETE! See the Texinfo documentation instead. You can read it either in Emacs or with the standalone **info** program.

The program **dvips** takes a DVI file *file* [*.dvi*] produced by TeX (or by some other processor such as GFtoDVI) and converts it to PostScript, sending the output to a file or directly to a printer. The DVI file may be specified without the *.dvi* extension. Fonts used may either be resident in the printer or defined as bitmaps in PK files, or a ‘virtual’ combination of both. If the **mktexpk** program is installed, **dvips** will automatically invoke METAFONT to generate fonts that don’t already exist.

For more information, see the Texinfo manual *dvips.texi*, which should be installed somewhere on your system, hopefully accessible through the standard Info tree.

OPTIONS

- a** Conserve memory by making three passes over the *.dvi* file instead of two and only loading those characters actually used. Generally only useful on machines with a very limited amount of memory, like some PCs.
- A** Print only odd pages (TeX pages, not sequence pages).
- b num** Generate *num* copies of each page, but duplicating the page body rather than using the *#numcopies* option. This can be useful in conjunction with a header file setting *\bop-hook* to do color separations or other neat tricks.
- B** Print only even pages (TeX pages, not sequence pages).
- c num** Generate *num* copies of every page. Default is 1. (For collated copies, see the **-C** option below.)
- C num** Create *num* copies, but collated (by replicating the data in the PostScript file). Slower than the **-c** option, but easier on the hands, and faster than resubmitting the same PostScript file multiple times.
- d num** Set the debug flags. This is intended only for emergencies or for unusual fact-finding expeditions; it will work only if **dvips** has been compiled with the **DEBUG** option. If nonzero, prints additional information on standard error. For maximum information, you can use ‘-1’. See the Dvips Texinfo manual for more details.
- D num** Set the resolution in dpi (dots per inch) to *num*. This affects the choice of bitmap fonts that are loaded and also the positioning of letters in resident PostScript fonts. Must be between 10 and 10000. This affects both the horizontal and vertical resolution. If a high resolution (something greater than 400 dpi, say) is selected, the **-Z** flag should probably also be used.
- e num** Make sure that each character is placed at most this many pixels from its ‘true’ resolution-independent position on the page. The default value of this parameter is resolution dependent. Allowing individual characters to ‘drift’ from their correctly

rounded positions by a few pixels, while regaining the true position at the beginning of each new word, improves the spacing of letters in words.

- E** makes **dvips** attempt to generate an EPSF file with a tight bounding box. This only works on one-page files, and it only looks at marks made by characters and rules, not by any included graphics. In addition, it gets the glyph metrics from the *tfm* file, so characters that lie outside their enclosing *tfm* box may confuse it. In addition, the bounding box might be a bit too loose if the character glyph has significant left or right side bearings. Nonetheless, this option works well for creating small EPSF files for equations or tables or the like. (Note, of course, that **dvips** output is resolution dependent and thus does not make very good EPSF files, especially if the images are to be scaled; use these EPSF files with a great deal of care.)
- f** Run as a filter. Read the *.dvi* file from standard input and write the PostScript to standard output. The standard input must be seekable, so it cannot be a pipe. If you must use a pipe, write a shell script that copies the pipe output to a temporary file and then points **dvips** at this file. This option also disables the automatic reading of the *PRINTER* environment variable, and turns off the automatic sending of control D if it was turned on with the *-F* option or in the configuration file; use *-F* after this option if you want both.
- F** Causes Control-D (ASCII code 4) to be appended as the very last character of the PostScript file. This is useful when **dvips** is driving the printer directly instead of working through a spooler, as is common on extremely small systems. **NOTE! DO NOT USE THIS OPTION!**
- G** Causes **dvips** to shift non-printing characters to higher-numbered positions. This may be useful sometimes.
- h name** Prepend file *name* as an additional header file. (However, if the name is simply '-' suppress all header files from the output.) This header file gets added to the PostScript *userdict*.
- i** Make each section be a separate file. Under certain circumstances, **dvips** will split the document up into 'sections' to be processed independently; this is most often done for memory reasons. Using this option tells **dvips** to place each section into a separate file; the new file names are created replacing the suffix of the supplied output file name by a three-digit sequence number. This option is most often used in conjunction with the *-S* option which sets the maximum section length in pages. For instance, some phototypesetters cannot print more than ten or so consecutive pages before running out of steam; these options can be used to automatically split a book into ten-page sections, each to its own file.
- j** Download only needed characters from Type 1 fonts. This is the default in the current release. Some debugging flags trace this operation. You can also control partial downloading on a per-font basis, via the **psfonts.map** file.
- k** Print crop marks. This option increases the paper size (which should be specified, either with a paper size special or with the *-T* option) by a half inch in each dimension. It translates each page by a quarter inch and draws cross-style crop marks. It is mostly useful with typesetters that can set the page size automatically.

- K** This option causes comments in included PostScript graphics, font files, and headers to be removed. This is sometimes necessary to get around bugs in spoolers or PostScript post-processing programs. Specifically, the `%%Page` comments, when left in, often cause difficulties. Use of this flag can cause some included graphics to fail, since the PostScript header macros from some software packages read portions of the input stream line by line, searching for a particular comment. This option has been turned off by default because PostScript previewers and spoolers have been getting better.
- l num** The last page printed will be the first one numbered *num*. Default is the last page in the document. If the *num* is prefixed by an equals sign, then it (and any argument to the `-p` option) is treated as a sequence number, rather than a value to compare with `\count0` values. Thus, using `-l =9` will end with the ninth page of the document, no matter what the pages are actually numbered. On the other hand, if *num* is suffixed by `‘.SEQ’`, the SEQth occurrence of *num* is used; for example, `-l 99.2` says to end processing with the second page numbered 99 in the document.
- m** Specify manual feed for printer.
- mode mode**
Use *mode* as the Metafont device name for path searching and font generation. This overrides any value from configuration files. With the default paths, explicitly specifying the mode also makes the program assume the fonts are in a subdirectory named *mode*.
- M** Turns off the automatic font generation facility. If any fonts are missing, commands to generate the fonts are appended to the file *missfont.log* in the current directory; this file can then be executed and deleted to create the missing fonts.
- n num** At most *num* pages will be printed. Default is 100000.
- N** Turns off structured comments; this might be necessary on some systems that try to interpret PostScript comments in weird ways, or on some PostScript printers. Old versions of TranScript in particular cannot handle modern Encapsulated PostScript.
- noomega**
This will disable the use of Omega extensions when interpreting DVI files. By default, the additional opcodes *129* and *134* are recognized by dvips as Omega or pTeX extensions and interpreted as requests to set 2-byte characters.
- noptex**
This will disable the use of pTeX extensions when interpreting DVI files. By default, the additional opcodes *130* and *135* are recognized by dvips as pTeX extensions and interpreted as requests to set 3-byte characters, and *255* as request to change the typesetting direction.

The only drawback is that the virtual font array will (at least temporarily) require 65536 or more positions instead of the default 256 positions, i.e., the memory requirements of dvips will be somewhat larger. If you find this unacceptable or encounter another problem with the Omega or pTeX extensions, you can switch off the pTeX extension by using **-noptex**, or both by using **-noomega** (but please do send a bug report if you find such problems - see the bug address in the **AUTHORS** section below).

-o name

The output will be sent to file *name*. If no file name is given (i.e., **-o** is last on the command line), the default name is *file.ps* where the *.dvi* file was called *file.dvi*; if this option isn't given, any default in the configuration file is used. If the first character of the supplied output file name is an exclamation mark, then the remainder will be used as an argument to *popen*; thus, specifying *!lpr* as the output file will automatically queue the file for printing. This option also disables the automatic reading of the *PRINTER* environment variable, and turns off the automatic sending of control D if it was turned on with the *-F* option or in the configuration file; use *-F* after this option if you want both.

-O offset

Move the origin by a certain amount. The *offset* is a comma-separated pair of dimensions, such as *.1in,-.3cm* (in the same syntax used in the *papersize* special). The origin of the page is shifted from the default position (of one inch down, one inch to the right from the upper left corner of the paper) by this amount.

-p num Just like *-l* but for the first page in the document.

-pp pagelist

A comma-separated list of pages and ranges (a-b) may be given, which will be interpreted as *\count0* values. Pages not specified will not be printed. Multiple **-pp** options may be specified or all pages and page ranges can be specified with one **-pp** option.

-P printername

Sets up the output for the appropriate printer. This is implemented by reading in *config.printername*, which can then set the output pipe (as in, *!lpr -Pprintername* as well as the font paths and any other *config.ps* defaults for that printer only. Note that *config.ps* is read before *config.printername*. In addition, another file called *%dvi/src* is searched for immediately after *config.ps*; this file is intended for user defaults. If no **-P** command is given, the environment variable *PRINTER* is checked. If that variable exists, and a corresponding configuration file exists, that configuration file is read in.

-q Run in quiet mode. Don't chatter about pages converted, etc.; report nothing but errors to standard error.

-r Stack pages in reverse order. Normally, page 1 will be printed first.

-R[0|1|2]

Run securely. **-R2** disables both shell command execution in *\special{}* (via backticks ```) and config files (via the *E* option), and opening of any absolute filenames. **-R1**, the default, forbids shell escapes but allows absolute filenames. **-R0** allows both. The config file option is *z*.

-s Causes the entire global output to be enclosed in a save/restore pair. This causes the file to not be truly conformant, and is thus not recommended, but is useful if you are driving the printer directly and don't care too much about the portability of the output.

-S num Set the maximum number of pages in each 'section'. This option is most commonly used with the *-i* option; see that documentation above for more information.

-t papertype

This sets the paper type to *papertype*. The *papertype* should be defined in one of the configuration files, along with the appropriate code to select it. (Currently known types include **letter**, **legal**, **ledger**, **a4**, **a3**). You can also specify **-t landscape**, which rotates a document by 90 degrees. To rotate a document whose size is not letter, you can use the *-t* option twice, once for the page size, and once for landscape. You should not use any *-t* option when the DVI file already contains a *papersize* special, as is done by some LaTeX packages, notably hyperref.sty.

The upper left corner of each page in the *.dvi* file is placed one inch from the left and one inch from the top. Use of this option is highly dependent on the configuration file. Note that executing the **letter** or **a4** or other PostScript operators cause the document to be nonconforming and can cause it not to print on certain printers, so the paper size should not execute such an operator if at all possible.

-T papersize

Set the paper size to the given pair of dimensions. This option takes its arguments in the same style as *-O*. It overrides any paper size special in the dvi file.

-u psmapfile

Set *psmapfile* to be the file that dvips uses for looking up PostScript font aliases. If *psmapfile* begins with a + character, then the rest of the name is used as the name of the map file, and the map file is appended to the list of map files (instead of replacing the list). In either case, if *psmapfile* has no extension, then **.map** is added at the end.

-U Disable a PostScript virtual memory saving optimization that stores the character metric information in the same string that is used to store the bitmap information. This is only necessary when driving the Xerox 4045 PostScript interpreter. It is caused by a bug in that interpreter that results in ‘garbage’ on the bottom of each character. Not recommended unless you must drive this printer.

-v Print the **dvips** version number and exit.

-V Download non-resident PostScript fonts as bitmaps. This requires use of ‘gsftopk’ or ‘pstopk’ or some other such program(s) in order to generate the required bitmap fonts; these programs are supplied with **dvips**.

-x num Set the magnification ratio to *num*/1000. Overrides the magnification specified in the *.dvi* file. Must be between 10 and 100000. Instead of an integer, *num* may be a real number for increased precision.

-X num

Set the horizontal resolution in dots per inch to *num*.

-y num Set the magnification ratio to *num*/1000 times the magnification specified in the *.dvi* file. See **-x** above.

-Y num

Set the vertical resolution in dots per inch to *num*.

-z Pass **html** hyperdvi specials through to the output for eventual distillation into PDF. This is not enabled by default to avoid including the header files unnecessarily, and use of temporary files in creating the output.

- Z** Causes bitmapped fonts to be compressed before they are downloaded, thereby reducing the size of the PostScript font-downloading information. Especially useful at high resolutions or when very large fonts are used. Will slow down printing somewhat, especially on early 68000-based PostScript printers.

SEE ALSO

afm2tfm(1), tex(1), mf(1), dvitype(1), lpr(1), *dvips.texi*, <https://tug.org/dvips>.

ENVIRONMENT

Dvipsk uses the same environment variables and algorithms for finding font files as TeX and its friends do. See the documentation for the Kpathsea library for details. (Repeating it here is too cumbersome.)

KPATHSEA_DEBUG: Trace Kpathsea lookups; set to -1 for complete tracing.

PRINTER: see above.

NOTES

PostScript is a registered trademark of Adobe Systems Incorporated.

AUTHOR

Tomas Rokicki; extended to virtual fonts by Don Knuth. Path searching and configuration modifications by Karl Berry.

Maintained in TeX Live; please send bug reports or other correspondence to tex-k@tug.org (<https://lists.tug.org/tex-k>).